

Documentation

as of: 03/29/2010



opsi

Version 3.4

installation manual

opsi-server

open pc server integration

boot- and installation server for workstation PC's



uib gmbh
Bonifaziusplatz 1B,
55118 Mainz
Tel.: +49 6131-275610
www.uib.de
info@uib.de

Table of Contents

1 INTRODUCTION.....	6
1.1 Steps for installation and starting.....	6
1.1 Hardware requirement.....	6
2 OPSI-SERVER BASE INSTALLATION.....	7
2.1 Starting of a VMware-Machine.....	7
2.2 Installation of a Debian (lenny) System with aptitude.....	8
2.3 Installation from the opsi-server-CD.....	9
2.4 Installation on an univention corporate server (UCS 2.x).....	11
2.5 Installation on openSUSE 10.3/11.0.....	12
3 LANGUAGE AND NETWORK CONFIGURATION.....	14
3.1 Language configuration.....	14
3.2 „1stboot“.....	14
3.3 Second start	16
3.4 Terminal window.....	18
3.5 Check and if necessary correct the network connection.....	18
4 UPDATE AND CONFIGURATION OF OPSISERVER.....	19
4.1 Proxy entry in apt-configuration.....	19
4.2 Update of the opsi-server.....	19
4.3 Checking the java configuration.....	19
4.4 Change passwords.....	20
4.5 Administrate the groups opsiadmin / pcpatch.....	20
5 DHCP-CONFIGURATION.....	21
5.1 Important.....	21
5.2 Using DHCP-Server at the opsi-Server.....	21
5.3 Using external DHCP-Server.....	21
5.4 Checking the backend configuration for DHCP entries.....	22

6	INSTALL AND CHECK OF THE ACTIVATION FILE.....	22
7	INSTALL THE MINIMAL OPSI-PRODUCTS.....	23
7.1	Download via browser.....	23
7.2	Download via wget (recommended).....	23
8	START OF THE OPSI-CONFIGED.....	24
9	OPSI-CLIENTS.....	25
9.1	Integration of existing clients.....	25
9.2	Creating a new client.....	25
10	FIRST TESTS.....	26
10.1	Hardwareinventory with the netboot product hwinvent.....	26
10.2	Hard- and Softwareinventory with the products hwaudit and swaudit.....	26
11	OS-INSTALLATION: COMPLETE THE BASE PACKAGE FOR WINDOWS.....	26
11.1	Windows 2000, XP, 2003.....	26
11.1.1	Copy the i368 directory.....	26
11.2	Windows Vista / 2008 / Windows 7.....	27
11.2.1	Creating a PE.....	27
11.2.1.1	unattend.xml.....	28
11.2.1.2	Driver integration.....	29
11.2.2	WinVista / Windows 2008 64-Bit version	29
11.2.2.1	Creating a 64-Bit Vista-PE.....	29
11.2.3	Providing the installation files.....	30
11.2.4	Log files of the installation.....	30
11.3	Windows product key.....	31
11.4	Start the Windows installation.....	31
11.5	For more infos (about integrating drivers) read the opsi manual.....	32
12	INSTALLATION OF PRODUCTS ON THE CLIENTS.....	32

12.1 opsi-adminutils.....	32
----------------------------------	-----------

13 SUPPLEMENT: UPDATE OF A OPSISERVER32

13.1 Update 3.3.1 to 3.4.....	32
--------------------------------------	-----------

13.1.1 Documentation.....	32
13.1.2 Backup.....	32
13.1.3 Debian / Ubuntu.....	33
13.1.3.1 Register of the opsi 3.4 repository.....	33
13.1.3.2 Put in the opsi debian packages.....	33
13.1.4 Suse.....	33
13.1.5 Checking the backend configuration.....	33
13.1.6 MySQL Inventory Backend.....	35
13.1.7 Download of the new opsi products.....	35
13.1.8 Import of the new opsi products.....	35
13.1.9 Install and check the activation file.....	35
13.1.10 Final 'check' and rollout of the new preloginloader to the clients.....	36

13.2 Update 3.3 to 3.3.1.....	36
--------------------------------------	-----------

13.2.1 Documentation.....	36
13.2.2 Backup.....	37
13.2.3 Debian / Ubuntu.....	37
13.2.3.1 Register of the opsi 3.3.1 repository.....	37
13.2.3.2 Put in the opsi debian packages.....	37
13.2.4 Suse.....	38
13.2.5 Checking the backend configuration.....	38
13.2.6 MySQL Inventory Backend.....	39
13.2.7 Download of the new opsi products (all users).....	39
13.2.8 Download of the new opsi products (opsi-vista support customers only).....	39
13.2.9 Import of the new opsi products.....	40
13.2.10 Activating the new support for the USB and HD-Audio driver.....	40

13.3 Update 3.2 to 3.3.....	40
------------------------------------	-----------

13.3.1 Documentation.....	40
13.3.2 Register of the opsi 3.3 repository.....	40
13.3.3 Put in the opsi debian packages.....	41
13.3.4 Checking the backend configuration.....	41
13.3.5 Import of the new opsi products.....	42

13.4 Update 3.1 to 3.2.....	42
------------------------------------	-----------

13.4.1 Register of the opsi 3.2 repository.....	42
---	----

13.4.2 Put in the opsi debian packages.....	43
13.4.3 Import of the new opsi products.....	43
13.4.4 Checking the backend configuration.....	43
13.5 Update 3.0 to 3.1.....	44
13.5.1 Register of the opsi3.1 repository.....	44
13.5.2 Put in the opsi debian packages.....	44
13.5.3 Adapt the configuration.....	44
13.6 Update 2.5 to 3.0.....	45
13.6.1 Register of the opsi 3-repository.....	45
13.6.2 Put in the opsi Debian package	46
13.7 Update 2.4 to 2.5.....	47
13.8 Update 2.x to 2.4.....	47

1 Introduction

This instruction explain detailed installation and starting of an opsiserver. It starts from the provided installation package and lead to a the test installation of a client.

The shown network configuration is exemplary and relates to a net without concurrent DHCP-Server (for example an isolated test net with a opsiserver and clients for the first trials).

We approve urgently for the first trials with opsi in a test net separated from other DHCP-server. Temporarily should a connection to the main net be possible for download actual product packages.

For an integration in concomitant nets you can ask for consulting service from your office (uib) if necessary.

1.1 Steps for installation and starting

Three steps for an installing and starting of an opsi-server:

- (a) base installation of the server
- (b) adjustment the server: configuration of the network, password awarding, updating of the server, product download
- (c) complete the System Software Base Package for Windows from the original-CDs

After wards a client could be installed automatically.

For the base installation exists some versions to choose from your interest. For all these versions are the required data-packages in the internet or at the opsiserver-CD provided:

The method of base installation variants are described in chapter 2 of this introduction.

1.1 Hardware requirement

For a opsiserver the following hardware is recommended:

- Intel-x86-compatible PC
- network interface card assisted by standard-linux kernel
- a hard disk with 16 GB capacity
- a bootable CD-ROM-drive

Neither in test handling or in reality handling are the requirements at the capacity on the machine high. Primarily the servers working as file-server which requires a network

connection.

Working with a VMware-Machine needs a reasonable host computer. It's possible for test status that an other VMware-machine work as client in the same host computer.

2 opsi-server base installation

This chapter describe three version of realization for an opsi-server. If all steps are successful you get an identical server system, which is prepared for configuration and starting. You can choose your way realizing an opsi-server and ignore the other stages. At the end you should update your system according chapter 'Update of the opsi-server'.

2.1 Starting of a VMware-Machine

A opsi-server can be installed as a virtual machine because the required computer speed can be low. For VMware a corresponding machine is prepared. The data files are available on the opsi-server-CD or in the internet. For handling free of charge VM-ware-player is adequate.

If you already installed a complete VMware software or a VMware player, you only need few mouse clicks for a opsi-server base installation:

- Copy the data 'opsi3.4-servervm.zip' from CD in a directory or download it from the internet.
- Unzip the data and a directory 'opsiserver' will be generated.
- Start the VMware-player. Search with the data browser the directory 'opsiserver' and choose the data 'opsiserver.vmx'. Sometime you get a message that CDROM- and floppy-disk device have another address – you can ignore this message. The virtual machine boots.

The VMware-player is free of charge for all system software on vmware.com. Normally you can install it without problems, if the equipment of the host computer (specially memory) meet the needs of parallel running software system.

The virtual machine from uib is based on Linux. Properties for our host-system are described in the configuration file 'opsiserver.vmx'. If you run the opsi-server image under Windows or if your Linux system machine has another address, you have to adapt the file.

If you restart your system successfully you can go on with to the chapter 'Language and Network configuration'.

2.2 Installation of a Debian (lenny) System with aptitude

In this chapter we assume you are familiar with the debian-package system (topic informations of this topic you will find in appropriate books, on manual pages or under <http://www.debian.org/doc/>).

Please note that an opsiserver needs storage place in /opt/pcbin and /var/lib/opsi. In both directories a free space of minimum 8 GB is recommended.

We recommend the following installations:

```
aptitude install wget lsof host python-mechanize p7zip-full cabextract  
openbsd-inetd
```

opsi need a installed samba. Install it form Debian:

```
aptitude install samba samba-common smbclient smbfs samba-doc
```

or install samba from the Sernet repositories:

Add in the file '/etc/apt/sources.list':

```
deb http://ftp.sernet.de/pub/samba/tested/debian lenny main
```

and install samba with the commands:

```
aptitude update  
aptitude install sernet-cifs-mount sernet-samba sernet-samba-doc sernet-smbclient sernet-smbfs
```

If you want to use MySQL as Backend for Inventory and license management you will need the mysql-server as well:

```
aptitude install mysql-server
```

Working on a Ubuntu server you should also install: openbsd-inetd.

Check the opsiserver entry in /etc/hosts or the output of

```
getent hosts `hostname -f`
```

The result should be similar to

```
192.168.1.1 server.domain.tld server
```

If the Result isn't like that and contains for example 127.0.0.1 or localhost you should correct your /etc/hosts or your DNS before you continue with the installation.

To start with the installation of opsi add in the file '/etc/apt/sources.list':

```
deb http://download.uib.de/debian lenny opsi3.4
```

Execute the following orders:

```
aptitude update  
aptitude remove tftpd
```



```
update-inetd --remove tftpd
aptitude install opsi-atftpd
aptitude install opsi-depotserver
aptitude install opsi-configed
```

During the tftpd-installation you may be asked for the tftp directory. Answer with '/tftpboot'. The question after the multicast support you can answer with 'no'.

During the installation of the opsisconfd you will be asked for informations for a SSL certificate preparation.

See also the description under 'Update opsi 2.5 to 3.0'.

During the opsiserver installation you have to allow the patching of the files 'dhcpd.conf' and 'smb.conf'. Answer the question with 'yes'. Also you will be asked for a password for the user 'pcpatch'. Set a new password and please consider chapter 'Change of passwords'.

Cause you install opsi on an existing machine we assume of a correct network configuration. So you can go on with chapter 'Checking the java configuration'.

2.3 Installation from the opsi-server-CD

The computer will be complete new attached. The hard disk will be prepared and a linux base system installed supported with the opsi-tools 'sysbackup' or 'sysrestore'.


Attention: The installation delete the complete hard disk!

Steps:

Put the CD in the drive and reboot the computer.

The computer should boot now from the CD. If it not boot from CD, you have to change the BIOS-settings to allow a reboot from CD.


Booting from CD you see the following message



After few seconds waiting 'Boot from local drive ' automatically will choose and the


reboot from the hard disk starts. Please choose 'Install opsi depotserver'.

After loading and boot is finished you will get something like the following window:



Choose 'OK' to continue.

The following output looks like:



'Extracting server file system' will take a while (about 5 - 15 Minutes).

After extracting the Master Boot Record is written an the machine reboots.

Take off the CD.

If you start your system successfully go on with the chapter 'Language and Network configuration'.

2.4 Installation on an univention corporate server (UCS 2.x)

For opsi evaluation we recommend to use our VMware-Machine or a Debian based System

The Installation of opsi4ucs is possible on servers with the roles Master, Backup and Slave. Installation on Member servers is not possible.

The package opsi4ucs-ldap-schema has to be installed always on the master.

The following documentation is based on a installation on a Master server.

Insert the following informations in the file /etc/apt/sources.list:

```
deb http://apt.univention.de/2.0/unmaintained/ 2.0-0/all/  
deb http://apt.univention.de/2.0/unmaintained/ 2.0-0/i386/  
deb http://apt.univention.de/2.0/unmaintained/ 2.0-0/amd64/  
deb http://apt.univention.de/2.0/unmaintained/ 2.0-0/extern/  
deb-src http://apt.univention.de/2.0/unmaintained/ 2.0-0/source/
```

Add for UCS 2.1:

```
deb http://apt.univention.de/2.1/unmaintained/ 2.1-0/all/  
deb http://apt.univention.de/2.1/unmaintained/ 2.1-0/i386/  
deb http://apt.univention.de/2.1/unmaintained/ 2.1-0/amd64/  
deb http://apt.univention.de/2.1/unmaintained/ 2.1-0/extern/  
deb-src http://apt.univention.de/2.1/unmaintained/ 2.1-0/source/
```

Add for UCS 2.2:

```
deb http://apt.univention.de/2.2/unmaintained/ 2.2-0/all/  
deb http://apt.univention.de/2.2/unmaintained/ 2.2-0/i386/  
deb http://apt.univention.de/2.2/unmaintained/ 2.2-0/amd64/  
deb http://apt.univention.de/2.2/unmaintained/ 2.2-0/extern/  
deb-src http://apt.univention.de/2.2/unmaintained/ 2.2-0/source/
```

Add final:

```
deb http://<username>:<password>@download.uib.de/debian ucs2.0 opsi3.4
```

You have to displace <username> and <password> with your login data.

Complete the following orders:

```
aptitude update  
aptitude install opsi4ucs-ldap-schema  
aptitude install opsi4ucs
```

During the tftpd-installation you will possibly be asked for the tftp directory. Answer with '/var/lib/univention-client-boot/'. The question after the multicast support you can answer with 'no'.

During the installation you will be asked some questions – see also 2.3.

If you are installing on a UCS server role other than master please run the opsi4ucs join script at this point:

```
univention-join [options]
```

The opsi configuration editor can be installed optional as applet on the UCS-server.

Complete the following orders:

```
aptitude install opsi-configed  
/etc/init.d/opsiconfd restart
```

The applet can called up with the URL `https://<servername>:4447/configed`.

For using the opsi configuration editor the user has to be member of the group 'opsiadmin'. The group membership of an user can be configured with the univention-admin.

Please Notice:

The configurations in the at the opsi manual frequently mentioned file

`etc/opsi/backendManager.d/30_vars.conf`

is superseded by the configurations of the file

`/etc/opsi/backendManager.d/40_opsi4ucs.conf`

at opsi4ucs installations.

Cause you install opsi on an existing machine we assume of a correct network configuration. So you can go on with chapter 'Checking the java configuration'.

2.5 Installation on openSUSE 10.3/11.0

First general notes:

- These packages are tested with Open-Suse 10.3/11.0. (Opensuse 11.1 is not supported yet)
- uib gmbh approved for evaluation the usage of opsi-VM or a Debian or Ubuntu Systems because the product dependence could be dissolved comfortable.
- Support for Suse based systems afford uib gmbh in context of a Professional Support contract.

Necessary preparations:

- The command “hostname -f” must return a fully qualified domainname containing two dots, e.g. `opsiserver.uib.local`
- The command “getent hosts `hostname -f`” must return the ip address of the interface the clients should connect to. If the result is `127.0.0.2` please correct your `/etc/hosts`.
- Samba must be configured

- If the machine should also act as DHCP-server, the daemon dhcpd has to be configured and should be up and running

You can use zypper to add the opsi-SUSE-Repository:

```
zypper ar http://download.uib.de/suse/opsi3.4 opsi3.4
```

Depending on the used openSUSE version you will have to resolve some package dependencies. The following packages may be not part of the distribution:

- python-crypto
- python-mysql
- python-twisted-web2
- python-newt
- duplicity

The required packages may be available in the following community-repositories:

openSUSE 10.3

http://download.opensuse.org/repositories/devel:/languages:/python/openSUSE_10.3/
<http://download.opensuse.org/distribution/10.3/repo/oss/suse>
<http://download.opensuse.org/distribution/10.3/repo/non-oss/suse>
http://download.opensuse.org/repositories/home:/lrupp:/Factory/openSUSE_10.3
http://download.opensuse.org/repositories/home:/Saviq/openSUSE_10.3
http://download.opensuse.org/repositories/home:/jimfunk/openSUSE_10.3/

openSUSE 11.0

http://download.opensuse.org/repositories/devel:/languages:/python/openSUSE_11.0/
http://download.opensuse.org/repositories/home:/dsbhayangkara/openSUSE_11.0_Update/
http://download.opensuse.org/repositories/home:/Saviq/openSUSE_11.0/

After adding the repositories the installation of opsi can be started by executing:

```
zypper install opsi-depotserver  
zypper install opsi-configed  
rcopsiconfd restart  
rcopsipxeconfd restart
```

Cause you install opsi on an existing machine we assume of a correct network configuration. So you can go on with chapter 'Checking the java configuration'.

3 Language and Network configuration

Precondition: Base installation is finished and the system (re)booted.

3.1 Language configuration

The first step is to choose the preferred language:



Figure 1: Language selection

3.2 „1stboot“

For the work with the opsiserver it could be helpful to connect them with the internet directly. For network configuration start the script `1stboot.py`.




Figure 2: 1stboot.py start mask

Put in the configuration informations for your network and answer the questions.




Figure3: 1stboot.py: Input mask

In the following you will asked for:

- server name Name of this server (without domain) e.g. opsidepot
- domain DNS-Domain (not Windows-Domain) – the name has to include a point e.g. opsi.local
- ip address Address of this server e.g. 192.168.1.50
- netmask Net mask of this server e.g. 255.255.255.0
- country For the creation of the SSL-certificate: Identification of the nation (2 capital letter) e.g. DE
- state For the creation of the SSL-certificate: Identification of the federal state e.g. RPL
- city For the creation of the SSL-certificate: Identification of the city e.g. Mainz
- organization For the creation of the SSL-certificate: Identification of the company e.g. uib gmbh
- organisational unit For the creation of the SSL-certificate: Identification of the bureau (optional)
- email address For the creation of the SSL-certificate: mail address (optional)
- gateway IP-adress of the internet gateway e.g. 192.168.1.1
- proxy If useful for the internet access the proxy informations: e.g. http://myuser:mypass@192.168.1.5:8080
- DNS server ip address of the name server e.g. 192.168.1.1
- mail relay ip address of the mail server e.g. 192.168.1.1
- tftp server: As 'TFTP server' you put in IP-number of the server (= 'IP-

address') normally.

- Password of root Password of root

After finishing the program '1stboot.py' the machine will be rebooted.

A technical advice to the program 1stboot.py:

The program works with templates to modify the configuration files. If you work reapply with the program and want to edit the configuration files by yourself you find the template in:

`/var/lib/1stboot/templates/`

3.3 Second start

After the reboot login as 'root' with your password.

You are on the graphic surface of the opsiserver directly (for the surface a sustainable use of resources surface so-called window manager will used). For salutatory an „Iceweasel“-browser-window with furthermore instructions and a reference on the available handbook attend.

If you get a message that their is no network connection, you should reboot the computer before you are searching for the fault.



Figure 4: Graphic start surface of the opsiserver

If the network configuration information was correct you are able to grab per remote on the opsiserver:

- Per ssh (in linux systems always existent, under Windows with putty, s. <http://www.chiark.greenend.org.uk/~sgtatham/putty/>) you can hit on the command line of the server. As user name you use 'root' and authenticate with the root password.
- Per vnc (normally under Linux with the e.g. available vncviewer or krdc, under Windows e.g. with ultravnc, <http://www.uvnc.com/>) you can use per remote a graphic surface. The vnc-address will build out of the IP-address (or the server name by a already working name release) and a trailed „:1“. The password for the vnc access is „linux123“. You should change it soonest – how is describe in the next chapter.

3.4 Terminal window

In the following some orders has to put in the command line. It could be a fast way to get the wished result.

A window for the input of orders i.e. a terminal window you can get in different ways:

- Remote access per ssh on the opsiserver (see the last chapter)
- Open a terminal window in the graphic surface (directly on the opsiserver or per vnc) with a click on the terminal icon in the icon bar.
- Open a terminal window in the graphic surface (directly on the opsiserver or per vnc) with a right mouse click in the surface and the choice of „Terminal“.

Helpfully: the graphic surface has many working surfaces reachable with the choice buttons in the left upper corner of the display.

It's very advantageous to put instruction orders e.g. out of this handbook per cut and paste in a terminal window (as far as the application environment support this).

The default password for the vnc connection is „linux123“ - you have to change it, best change is directly:

Open a new terminal window and write:

```
vncpasswd
```

On the following question you have to put in your new password. Minimum are 8 characters.

General in productive systems should the vnc access be locked or only allowed tunnelled with over SSH for security reasons. If vnc is admitted for the internal network a firewall has to block the internet port.

3.5 Check and if necessary correct the network connection

If the network configuration is correct and the computer is connected with the internet you can access on any address in the internet with the browser in the start window.

If not everything works you have to open a terminal window (maybe the remote access isn't possible yet but the direct server surface) and prove the network connection usual checks.

You can access the following command in the terminal window

```
1stboot.py
```

and put in the network configuration again.

A reboot is forced with the order

```
reboot
```

If the network connection works, you can put in opsi packages or actualize them. And build the environment for the first installation test.

4 Update and configuration of opsiserver

4.1 Proxy entry in apt-configuration

Adapt if necessary the file

```
/etc/apt/apt.conf
```

on your network circumstances (put the right proxy in or comment/delete lines). You can edit your file with e.g. a program like „midnight commander“:

```
mc /etc/apt/apt.conf
```

4.2 Update of the opsiserver

Update the opsiserver with the commands:

```
aptitude update  
aptitude safe-upgrade
```

4.3 Checking the java configuration

Administrate the opsiservers and the connected clients with the program 'opsi-configed'. The program is written in Java and use minimum Java version 6 or version 1.6 (old version count).

To control the Java version call up

```
java -version
```

in a terminal window.

Adapt in a terminal window with `update-alternatives` the Java version if it's not indicated with minimum „1.6.0“:

```
update-alternatives --config java
```

```
There are 3 alternatives which provide `java'.
```

```
Selection      Alternative
```

```
-----  
+   1   /usr/lib/j2se/1.4/bin/java  
*   2   /usr/lib/j2sdk1.5-sun/bin/java  
    3   /usr/lib/j2re1.6-sun/bin/java
```

```
Press enter to keep the default[*], or type selection number: 3  
Using `/usr/lib/j2re1.6-sun/bin/java' to provide `java'.
```

4.4 Change passwords

On the system is a pseudo-user 'pcpatch' arranged. For installation of software packages the PC use the user 'pcpatch' and you can access the configuration data on designed shares.

The user 'pcpatch' has to be arranged with a correct password. Call in a terminal window the program 'opsi-admin' and the 'opsi-admin' will set the 'pcpatch-password for opsi, unix and samba (after sending the order you have to put in the password):

```
opsi-admin -d task setPcpatchPassword
```

4.5 Administrate the groups opsiadmin / pcpatch

The opsi administration is only allowed for user members in the UNIX-group 'opsiadmin'.

In the configured VMware-machine is only 'root' member of these group. If on the opsiserver e.g. a user 'Schneider' exists and belong also to the group 'opsiadmin' the group membership can be arranged and tested with the orders:

```
adduser schneider opsiadmin  
grep opsiadmin /etc/group
```

The grep-order put out (similar)

```
opsiadmin:x:993:root,schneider
```

All user which pack packages (opsi-makeproductfile), install (opsi-package-manager) or edit manuell configuration files have to be in the group 'pcpatch' additional:

```
adduser testuser pcpatch  
adduser schneider pcpatch
```

The test

```
grep pcpatch /etc/group
```

devote

```
pcpatch:x:992:testuser,schneider
```

root is allowed to do anything and have not to be explicit registered in the group.

To create a new admin user use commands like this:

```
useradd -m -s /bin/bash adminuser
passwd adminuser
smbpasswd -a adminuser
adduser adminuser opsiadmin
adduser adminuser pcpatch
```

5 DHCP-Configuration

5.1 Important

A correct working name resolving and DHCP is essential for opsi. To simplify the setup, the opsi-server VM is delivered with a running DHCP-Server. At the other hand in most productive environments a DHCP-Server exists and should be used together with opsi. Both alternatives are described below. See also the DHCP/DNS Chapter at the opsi-manual.

5.2 Using DHCP-Server at the opsi-Server

The DHCP-Server at the opsi-server VM is configured with no free leases, so no unknown client will get a IP-Number from this DHCP-Server.

If you create a client at the opsi-server it will also create a dhcp entry for this client. Therefore you have to supply the IP-number and the MAC-address.

5.3 Using external DHCP-Server

If you use an external DHCP-Server you may want to disable the DHCP-Server at the opsi-Server:

```
/etc/init.d/dhcp3-server stop
update-rc.d -f dhcp3-server remove
update-rc.d dhcp3-server stop 20 2 3 4 5 .
```

Next you have to configure your external DHCP-Server to tell the clients that our opsi-server is now the boot server. If your external DHCP runs on Linux you need the following entries for the clients in the `/etc/dhcp3/dhcpd.conf` file.

```
next-server <ip of opsi-server>;
filename "linux/pxelinux.0";
```

Replace <ip of opsi-server> by the IP-number of the opsi-Servers.

Using a Windows server the corresponding entries may be `bootserver` or `startserver` and `bootfile` or `startfile`.

If you create a client at the opsi-server you have to supply the MAC-address, but no IP-number.

5.4 Checking the backend configuration for DHCP entries

In the file `/etc/opsi/backendManager.d/30_vars.conf` is defined witch backend manage of opsi be used (`BACKEND_FILE31`, `BACKEND_FILE`, `BACKEND_LDAP`). The default backend is `BACKEND_FILE31`. In the entry `clientManagingBackend` may be controlled if opsi also assume the local DHCP configuration. This is sensible if the DHCP-server of the opsi-server will be used (default). The accordant entry is:

```
self.clientManagingBackend = [ BACKEND_DHCPD, BACKEND_FILE31 ]
```

If the local DHCP isn't used also the `BACKEND_DHCPD` not required:

```
self.clientManagingBackend = BACKEND_FILE31
```

After adapting the backend configuration the 'opsi-confd' has to be restarted:

```
/etc/init.d/opsiconfd restart
```

6 Install and check of the activation file

Even opsi is open source, there are some components which are not free at the moment. These components are developed in a co-funding project which means that until the complete development costs are payed by co-funders, they are only allowed to use by the co-funders or for evaluation purposes. If we have earned the development cost we will give these modules for everybody for free. To control the use of these components until they are free there is a activation file `/etc/opsi/modules`, which is protected against changes via electronic signature. If this activation file doesn't exist, only the free parts of opsi will work.

If you need for evaluation a temporary valid activation file please contact info@uib.de. If you become a co-funder, you will get a unlimited activation file.

You may check your activation state with one of the following methods:




Fig. 5: Display of activation state in opsi-configed

Using the opsi-configed choose the menu entry Help/opsi-Module which shows a window with the activation state.

At the command line you may use the command `opsi-admin` with the method `getOpsiInformation_hash`. (Remark: Never give your activation file or the output of this command to third people without deleting the signature).

```
opsi-admin -d method getOpsiInformation_hash
{
  "opsiVersion" : "3.4.0.0",
  "modules" :
  {
    "customer" : "uib GmbH",
    "vista" : false,
    "license_management" : true,
    "expires" : "never",
    "valid" : true,
    "signature" : "THIS-IS-NOT-A-VALID-SIGNATURE",
    "vpn" : true
  }
}
```

7 Install the minimal opsi-products

Get the actual necessary opsi-packages in the new opsi-package format.

7.1 Download via browser

Follow the link on the graphic surface of the start window and attend the details than you can download the packages and install them after wards.

7.2 Download via wget (recommended)

You are able to do the procedure also on the command line of the terminal window:

```
cd /home/opsiproducts
wget -r -ll -nd -nc -A '*.opsi' http://download.uib.de/opsi3.4/produkte/essential
```

If the 'wget' command failed so possible the environment variable 'http_proxy' has to been set on the correct proxy string (e.g. http_proxy=http://192.168.1.5:8080/)

Put in the downloaded packages on your server and install them so the product is available for the clients. The interactive installation of a opsi package start with

```
opsi-package-manager -i <paketname>.opsi
```

The following order installed all downloaded packets successive:

```
opsi-package-manager -i *.opsi
```

Please notice that the OS-Installation products like winxpro and win2k aren't ready for action after installation. The installation has to be supplemented by the installation files of the accordant installation mediums (see chapter 11 OS-Installation: Complete the base package for Windows at page 26 of this manual).

You are invited to download more opsi-products from download.uib.de and install them on your opsiserver similarly.

8 Start of the opsi-configed

Opsi offer with the opsi-configed a comfortable management interface.

You can start it different ways:

- If you are put in the adress in the browser (anywhere in the net)
`https://<opsiserver>:4447/configed` a web side with an embedded opsi-configed appear. Precondition is a installed java version ≥ 1.6 .
- Alternative you can click with the right mouse tab on the graphic surface to open teh context menu and choose the „opsi config editor“.
- The configuration editor is also component of the opsi-adminutils which also can be copied local on the client.

Log in with the member account of the group opsiadmin.

9 opsi-clients

9.1 Integration of existing clients

To integrate existing Windows clients in opsi the opsi-preloginloader have to be installed on these systems. There different ways to do this which are described in the opsi-manual at the chapter: 'Subsequent installation of the opsi-preloginloaders'. After you have done so, you should see the client at the crystal tab 'client selection'.

9.2 Creating a new client

You need a client (minimum 256 MB RAM) which is able to boot per PXE the network. For a first test we approve to download a corresponding vmware-image by download.uib.de (http://download.uib.de/vmware_pxeclient.zip). The advantage of vmware (virtuell hardware) is the support of the standard drivers from windows.

Now you have to create a client in the opsi system. Start the installation with a) the opsi-configed or b) the command line.

Graphic frontend of opsi-configed:

With menu item 'OpsiClient/Create new opsi client' and the description of IP-name, domain, client description, IP-number (which is only requested by the internal DHCP) and MAC-address you finished the client creation. The client will be created in the opsi database and (if so configured) at the same time as PXE-client at the DHCP configuration on the opsiserver.

Command line opsi-admin:

```
opsi-admin -d method createClient <clientname> <domain>  
<description> <notes> <ipAddress> <hardwareAddress>
```

e.g.:

```
opsi-admin -d method createClient pxevm uib.local "Testclient" ""  
192.168.0.5 00:0c:29:12:34:56
```

After you have done so, you should see the client at the crystal tab 'client selection'.

10 First Tests

10.1 Hardwareinventory with the netboot product hwinvent

After wards choosing the client and in the crystal tab 'netboot-Products' in the line of the wished system software (e.g. hwinvent) the action 'setup' choose and save with a click on the hook button.

Now reboot the client (over PXE), the hwinvent should be started. The client load after the reboot a linux-boot-image which scans the hardware and send the results back to the server.

After wards the software system will be installed.

10.2 Hard- and Softwareinventory with the products hwaudit and swaudit

After wards choosing the client and in the crystal tab 'product configuration' in the line of the wished system software (hwaudit and/or swaudit) the action 'setup' choose and save with a click on the hook button.

Now reboot the client, the installation of python (and after a reboot) the hwaudit and/or swaudit should be started. The client scans the hardware and/or software inventory and send the results back to the server.

11 OS-Installation: Complete the base package for Windows

The base package include only files for automatic system software installation – not the system software for his own.

If you want to test the automatic Windows 2000- or Windows XP-system software installation, you have to complete these packages.

11.1 Windows 2000, XP, 2003

11.1.1 Copy the i386 directory

a) copy the i386-directory of a installation-CD for Microsoft Win2k/WinXP Professional in the directory /opt/pcbin/install/win2k or /opt/pcbin/install/winxppro directory. After copy you have to change the rights of the i386/ directory:

```
chown -R opsiconfd:pcpatch i386/  
chmod -R ug+rw i386/
```

The file can be copied also over the network. Therefore you have to connect as user "pcpatch" by the approval "opt_pcbin" on the opsiserver. The corresponding directory

you will find under `install\winxpro` or `install\win2k`.

11.2 Windows Vista / 2008 / Windows 7

Because the Vista installation only starts from a Win32/Win64 environment we must build a PE-Image which is used to startup the installation.

"To install a 64-bit version of Windows you must use a 64-bit version of Windows PE. Likewise, to install a 32-bit version of Windows, you must use a 32-bit version of Windows PE."

<http://technet.microsoft.com/en-us/library/cc766093.aspx>

Therefore you need the Windows Automated Installation Kit (Windows AIK):

<http://www.microsoft.com/downloads/details.aspx?displaylang=en&FamilyID=696dd665-9f76-4177-a811-39c26d3b3b34>

Version date is 8/6/2009.

What you get is a ISO file which may be burned to CD or mounted by a virtual machine. The content of this CD must be installed in an OS mentioned in system requirements.

11.2.1 Creating a PE

Console commands for creating a Windows PE in 32- or 64-bit versions are nearly the same, except for the <ARCH> entries below. These have to be set to either `x86` , `amd64` or `ia64`.

1. Creating an environment:

Start a terminal as administrator (Start → Programs → Accessories → right click on „Command Prompt“ → Run as... → Administrator) and run the following command:

```
"%ProgramFiles%\Windows AIK\Tools\PETools\copype.cmd" <ARCH> C:\winpe
```

2. Prepare Image for opsi:

Start a terminal as administrator and run the following commands:

```
"%ProgramFiles%\Windows AIK\Tools\<ARCH>\imagex.exe" /mount  
"C:\winpe\winpe.wim" 1 "C:\winpe\mount"
```

```
echo c:\opsi\startnet.cmd >  
"C:\winpe\mount\Windows\System32\startnet.cmd"
```

(Remark: The file `startnet.cmd` will be created by the opsi linux boot image by executing the script `setup.py`. The `startnet.cmd` contains the call to `wpeinit`.)

```
"%ProgramFiles%\Windows AIK\Tools\<ARCH>\imagex.exe" /commit /unmount  
"C:\winpe\mount"
```

```
move "C:\winpe\winpe.wim" "C:\winpe\ISO\sources\boot.wim"
```

- ## 3. Copy the directory `C:\winpe\ISO` with the target name `winpe` to `/opt/pcbin/install/winvista/` respectively `/opt/pcbin/install/win2008`

Adjust the file access rights:

```
chown -R opsiconfd:pcpatch /opt/pcbin/install/winvista/winpe
```

11.2.1.1 unattend.xml

The control file for the unattended Installation is the `unattend.xml` which you will find below `/opt/pcbin/install/winvista/opsi`. If you make any modifications at this file, it should be backuped in a different directory, because the opsi directory is subject of updates in future versions of the opsi winvista package.

The `unattend.xml` delivered wit the opsi winvista package contains the activating of the Administrator account with the password 'nt123'.

Documentation to the `unattend.xml` you will find (after the installation of the WAIK) in the directory

```
\Program Files\Windows\Waik\docs\chms
```

11.2.1.2 Driver integration

The integration of drivers works at the usual in the opsi manual described way: Place your driver directories in `/opt/pcbin/install/winvista/drivers/drivers` and then call the `create_driver_links.py` script.

Please keep in mind that Vista only accept signed drivers. Therefor it is no good idea to use driver packs which contain none vista drivers like the driver packs from driverpacks.net.

11.2.2 WinVista / Windows 2008 64-Bit version

11.2.2.1 Creating a 64-Bit Vista-PE

1. Installation of the Windows AIK at Vista 64-Bit or Windows 2003 Server 64-Bit
2. Create a WinPE

Copy the file `boot.wim` from the Winvista-64-Bit-CD to the directory

```
C:\winpe_amd64\ISO\sources\
```

Remove the write protection from `boot.wim`

3. mount the image with:

```
"C:\Program Files\Windows AIK\Tools\amd64\imagex.exe"
```

```
/mountrw C:\winpe_amd64\ISO\sources\boot.wim 1
```

```
c:\winpe_amd64\mount
```

Edit with `Notepad.exe`

```
C:\WinPE_amd64\mount\Windows\System32\startnet.cmd
```

Delete the entry `wpeinit` and add the following line:

```
c:\opsi\startnet.cmd
```

(Remark: The file `startnet.cmd` will be created by the opsi Linux boot image by executing the script `winvista.py`. The `startnetcmd` contains the call to `wpeinit`.)

unmount the image

```
"C:\Program Files\Windows AIK\Tools\amd64\imagex.exe"
```

```
/unmount /commit C:\winpe_amd64\mount
```

Please note: At 64-Bit Vista also the archive **2** must be mounted and edited:

```
"C:\Program Files\Windows AIK\Tools\amd64\imagex.exe"  
/mountrw C:\winpe_amd64\ISO\sources\boot.wim 2
```

```
c:\winpe_amd64\mount
```

Edit with Notepad.exe

```
C:\WinPE_amd64\mount\Windows\System32\startnet.cmd
```

Delete the entry wpeinit and add the following line:

```
c:\opsi\startnet.cmd
```

Additional remove the files setup.exe and sources\setup.exe

Image unmounted

```
"C:\Program Files\Windows AIK\Tools\amd64\imagex.exe"  
/unmount /commit C:\winpe_amd64\mount
```

Copy the directory C:\WinPE_amd64\ISO with the target name winpe to

```
/opt/pcbin/install/winvista64/ respectively
```

```
/opt/pcbin/install/win2008_64/
```

Adjust the file access rights:

```
chown -R opsiconfd:pcpatch /opt/pcbin/install/winvista64/winpe
```

11.2.3 Providing the installation files

Copy the complete installation DVD to

```
/opt/pcbin/install/winvista/vistasrc
```

Adjust the file access rights:

```
chown -R opsiconfd:pcpatch /opt/pcbin/install/winvista/vistasrc
```

11.2.4 Log files of the installation

- c:\Windows\Panther\setupact.log:
Log until the end of setup phase 4 (running under WinPE)
- c:\Windows\Panther\setupact.err:
Error log until the end of setup phase 4 (running under WinPE)
- c:\Windows\Panther\UnattendGC\setupact.log:
Log since specialize phase
- c:\Windows\Panther\UnattendGC\setupact.err:
Error log since specialize phase
- c:\Windows\System32\Winevt\Logs*

- `c:\Windows\ntbtlog.txt` (only with activated startup protocol)

11.3 Windows product key

If you using the opsi license management module, you may administrate your Windows productkeys by the license management. Informations how to do this you will find at the opsi manual.

If you don't want to use the license management module, the productkey can be provided by using product properties:

If you still have created a client you can use the opsi management interface to enter the product key:

- choose a client
- change to the tab 'nettboot products'
- select the product (e.g. winxpro)
- change to the product property 'productkey' (on the right lower corner of the opsi management interface)
- type in your key
- leave the input field and save the changes

A other possibility is to use the command line. With out giving a special client you will read / change the server default.

To read the server default use:

```
opsi-admin -d method getProductProperties_hash winxpro
```

To set the server default use (it has to be one line):

```
opsi-admin -d method setProductProperty winxpro "productkey" "ABCDE-FGHIJ-KLMNO-QRTUV-WXYZ1"
```

11.4 Start the Windows installation

To startup a windows installation:

- choose a client
- change to the tab 'nettboot products'
- select the product (e.g. winxpro)
- set the 'action request' to setup
- save the changes by clicking the red hook (which changes to green)

Now the client should load the opsi linux bootimage via network and start it. Before the

windows installations starts you have to confirm once.

11.5 For more infos (about integrating drivers) read the opsi manual

The handling of the opsi-server is explained in the opsi-manual version 3.4

12 Installation of products on the clients

You can access the opsi-configed webapplet with `https://<servername>:4447/configed` and start the installation of other products.

Important products are:

12.1 opsi-adminutils

The product opsi-adminutils includes the opsi-configed for a local installation e.g. on a system administrator computer.

13 Supplement: Update of a opsi-server

13.1 Update 3.3.1 to 3.4

13.1.1 Documentation

Please read the opsi 3.4 changes documentation in the opsi-manual.

13.1.2 Backup

It is always a good idea to make a backup before relevant changes to the system
At this release there are major changes at the MySQL-Backend. So a backup of the existing data base is strongly recommended.

This is a possible command to do this job:

```
/etc/init.d/mysql stop  
cp -a /var/lib/mysql /var/lib/mysql.backup  
/etc/init.d/mysql start
```


13.1.3 Debian / Ubuntu

13.1.3.1 Register of the opsi 3.4 repository

In order to avoid that an update to 3.4 happens accidentally, the debian package for opsi 3.4 is in a specific repository. Delete in `/etc/apt/sources.list` the entry:

```
deb http://download.uib.de/debian etch opsi3.3.1
```

and put in:

For Debian Etch, Ubuntu Dapper/Edgy/Feisty (i386/amd64):

```
deb http://download.uib.de/debian lenny opsi3.4
```

For Debian Lenny, Ubuntu Hardy (i386/amd64):

```
deb http://download.uib.de/debian lenny opsi3.4
```

Remark: Ubuntu Jaunty isn't supported yet.

Execute `aptitude update`.

13.1.3.2 Put in the opsi debian packages

Put in the packages with following order:

```
aptitude safe-upgrade
```

If you be asked on upgrading which version of a configuration file you wish to apply you should choose the newest version. If not you should know exactly what you do e.g. you don't choose the newest version because you want an other as the default File31-Backend.

13.1.4 Suse

Important: Please do not upgrade from opsi3.3 to opsi3.4 directly. If you are using opsi3.3 please upgrade to opsi3.3.1 first or contact uib-opsi-support.

In order to update execute the following commands:

```
zypper rr opsi3.3.1
zypper ar http://download.uib.de/suse/opsi3.4 opsi3.4
zypper update
```

13.1.5 Checking the backend configuration

In the file `/etc/opsi/backendManager.d/30_vars.conf` is defined which backend manage

of opsi be used (`BACKEND_FILE31`, `BACKEND_MYSQL`, `BACKEND_LDAP`).

The default backend is `BACKEND_FILE31`.

The backend `BACKEND_FILE` is deprecated - it is not supported anymore.

In the entry `clientManagingBackend` may be controlled if opsi also assume the local DHCP configuration. This is sensible if the DHCP-server of the opsi server will be used (default). The accordant entry is:

```
self.clientManagingBackend = [ BACKEND_DHCPD, BACKEND_FILE31 ]
```

If the local DHCP isn't used also the `BACKEND_DHCPD` not required:

```
self.clientManagingBackend = BACKEND_FILE31
```

For the hard- and software inventory you have since opsi 3.3 two possibilities: `BACKEND_FILE31` or `BACKEND_MYSQL`. One of these you have to enter independent which backend is used normally:

```
self.swinventBackend = BACKEND_FILE31
self.hwinventBackend = BACKEND_FILE31
```

The license management module only works with the `MYSQL-Backend` and need also this Backend for hardware and software inventory. In order to use the license management insert:

```
self.swinventBackend      = BACKEND_MYSQL
self.hwinventBackend      = BACKEND_MYSQL
self.licenseBackend       = BACKEND_MYSQL
```

For the logging there is since opsi 3.3 a own Backend: `BACKEND_FILE31`. These you have to enter independent which backend is used normally:

```
self.loggingBackend = BACKEND_FILE31
```

After adapting the backend configuration the 'opsiconfd' has to be restarted:

```
/etc/init.d/opsiconfd restart
```

13.1.6 MySQL Inventory Backend

If you use the MySQL-Backend for inventory and license management you should call

```
/usr/share/opsi/init-opsi-mysql-db.py
```

Perhaps you need to install the mysql-server before you can run this script:

```
aptitude install mysql-server
```

13.1.7 Download of the new opsi products

Fetch the actual necessary opsi packages:

```
cd /home/opsiproducts
mkdir opsi34
cd opsi34
wget -r -ll -nc -nd -A '*.opsi' http://download.uib.de/opsi3.4/produkte/essential
```

13.1.8 Import of the new opsi products

The downloaded packages has to be installed on the server to be available for the clients. The interactive installation of an opsi package happen with the aid of the order:

```
opsi-package-manager -i <package file name>
```

The following order install the downloaded packages successive:

```
opsi-package-manager -i *.opsi
```

13.1.9 Install and check the activation file

The use of non free components of the opsi installation is controlled by the activation file `/etc/opsi/modules` .(See also Chapter 6 Install and check of the activation file at page 22 in this manual).

While the Release Candidate phase you will find a activation file which is valid until 31.8.2009 at <http://download.uib.de/opsi3.4/modules> . You should copy these file to `/etc/opsi` using the root account. You may do this with:

```
cd /etc/opsi
wget http://download.uib.de/opsi3.4/modules
```

You may check your activation state with:

```
opsi-admin -d method getOpsiInformation_hash
```

With this activation file you have the possibility to test our license management as well as our Vista / Win7 Support with the new opsiclientd from the preloginloader 3.4. If you are testing the opsiclientd but don't want to buy it, so please remember to change all clients before the evaluation time ends to the legacy prelogin mode. Which mode of the preloginloader should be installed is controlled by the product property 'client_servicetype' and the file

`opt/pcbin/install/preloginloader/files/opsi/cfg/config.ini` with the entry:

```
[installation]
;client_servicetype=prelogin
client_servicetype=opsiclientd
```

You may check the server default for the product property 'client_servicetype' with:

```
opsi-admin -d method getProductProperties_hash preloginloader
```

You may set the server default of product property 'client_servicetype' to 'prelogin' with:

```
opsi-admin -d method setProductProperty preloginloader "client_servicetype" "prelogin"
```

If you have no activation for 'vista', you should work with the 'prelogin' mode. The opsiclientd will not work without the 'vista' activation.

13.1.10 Final 'check' and rollout of the new preloginloader to the clients

All parts of a opsi release are designed to work together. It is no good idea to try running opsi with packages that are mixed from different releases. So you should make a final check if all your packages (Linux-Packages as well as opsi packages) have at least the release version that was published in the release mail on forum.opsi.org or in the announce mailing list.

To avoid running in mixed environments you should rollout the new preloginloader to all your clients soon. If you forget this task, you will perhaps find your self in the situation, that the clients can't connect to the server any more after the next server upgrade.

13.2 Update 3.3 to 3.3.1

13.2.1 Documentation

Please read the opsi 3.3.1 changes documentation in the opsi-manual.

13.2.2 Backup

It is always a good idea to make a backup before relevant changes to the system
If you already have a gina.dll installed which is different from the original msgina (e.g. Novells nwgina) and chained this gina with the opsi-pgina, so note that the Registry entries of the opsi pgina now located under
HKEY_LOCAL_MACHINE\SOFTWARE\opsi.org\preloginloader

Regarding the major changes in the structure of the OS-Installation products like winxpro, a backup of the directories of these products below /opt/pcbin/install is strongly recommended.

This is a possible command to do this job:

```
cd /opt/pcbin/install  
tar cvf /home/opsiproducts/winxpro-pre3331.tar winxpro
```

13.2.3 Debian / Ubuntu

13.2.3.1 Register of the opsi 3.3.1 repository

In order to avoid that an update to 3.3.1 happens accidentally, the debian package for opsi 3.3.1 is in a specific repository. Delete in /etc/apt/sources.list the entry:

```
deb http://download.uib.de/debian etch opsi3.3
```

and put in:

For Debian Etch, Ubuntu Dapper/Edgy/Feisty (i386/amd64):

```
deb http://download.uib.de/debian etch opsi3.3.1
```

For Debian Lenny, Ubuntu Hardy (i386/amd64):

```
deb http://download.uib.de/debian lenny opsi3.3.1
```

Execute `apt-get update`.

13.2.3.2 Put in the opsi debian packages

Put in the packages with following order:

```
apt-get upgrade
```

If you be asked on upgrading which version of a configuration file you wish to apply you should choose the newest version. If not you should know exactly what you do e.g. you

don't choose the newest version because you want an other as the default File31-Backend.

13.2.4 Suse

In order to update execute the following commands:

```
zypper rr opsi3.3
zypper ar http://download.uib.de/suse/opsi3.3.1 opsi3.3.1
mkdir /tmp/opsi3.3.1
cd /tmp/opsi3.3.1
wget -Arpm -nH -nd -np -r http://download.uib.de/suse/opsi3.3.1/RPMS/noarch
rm opsi-depotserver* opsi-atftp*
zypper install python-twisted-web python-twisted-conch
rpm -U --nopostun *.rpm
rcopsiconfd restart
rcopsipxeconfd restart
```

13.2.5 Checking the backend configuration

In the file `/etc/opsi/backendManager.d/30_vars.conf` is defined which backend manage of opsi be used (`BACKEND_FILE31`, `BACKEND_FILE`, `BACKEND_LDAP`).

The default backend is `BACKEND_FILE31`.

The backend `BACKEND_FILE` is deprecated - you should change to `BACKEND_FILE31`.

In the entry `clientManagingBackend` may be controlled if opsi also assume the local DHCP configuration. This is sensible if the DHCP-server of the opsiserver will be used (default). The accordant entry is:

```
self.clientManagingBackend = [ BACKEND_DHCPD, BACKEND_FILE31 ]
```

If the local DHCP isn't used also the `BACKEND_DHCPD` not required:

```
self.clientManagingBackend = BACKEND_FILE31
```

For the hard- and software inventory you have since opsi 3.3 two possibilities: `BACKEND_FILE31` or `BACKEND_MYSQL`. One of these you have to enter independent which backend is used normally:

```
self.swinventBackend = BACKEND_FILE31
self.hwinventBackend = BACKEND_FILE31
```

For the logging there is since opsi 3.3 a own Backend: BACKEND_FILE31. These you have to enter independent which backend is used normally:

```
self.loggingBackend = BACKEND_FILE31
```

After adapting the backend configuration the 'opsi-confd' has to be restarted:

```
/etc/init.d/opsiconfd restart
```

13.2.6 MySQL Inventory Backend

If you use the MySQL-Backend for inventory you should call

```
/usr/share/opsi/init-opsi-mysql-db.py
```

in order to reconfigure your database according to the new hwaudit.conf.

13.2.7 Download of the new opsi products (all users)

Fetch the actual necessary opsi packages:

```
cd /home/opsiproducts
mkdir opsi331
cd opsi331

wget -r -ll -nc -nd -A '*.opsi' http://download.uib.de/opsi3.3.1/produkte/essential
```

13.2.8 Download of the new opsi products (opsi-vista support customers only)

This chapter concerns only to customers of the opsi support for vista and preloginloader 3.4 which have an account to the opsi vista repository.

Fetch the actual necessary opsi packages from

<http://download.uib.de/abo/vista/opsi3.3.1> using your account user name and password:

```
cd /home/opsiproducts/opsi331
#the next command is one line
wget -r -ll -nc -nd --http-user=<user> --http-passwd=<password> -A '*.opsi'
http://download.uib.de/abo/vista/opsi3.3.1
#the same comman again not readable but for cut&paste
wget -r -ll -nc -nd --http-user=<user> --http-passwd=<password> -A '*.opsi' http://download.uib.de/abo/vista/opsi3.3.1
```

The new opsi-preloginloader 3.4-x replaces the legacy preloginvista product which should be deleted from the server with the following command:

```
opsi-package-manager -r preloginvista
```

The new preloginloader 3.4 replaces also the preloginloader 3.3.1 which have been downloaded before from the general repository. So please delete this package.

The new preloginloader 3.4 is described in the opsi-vista installation manual:
http://download.uib.de/opsi3.3.1/doku/opsi_v331_vista_installation_en.pdf

13.2.9 Import of the new opsi products

The downloaded packages has to be installed on the server to be available for the clients. The interactive installation of an opsi package happen with the aid of the order:

```
opsi-package-manager -i <package file name>
```

The following order install the downloaded packages successive:

```
opsi-package-manager -i *.opsi
```

The defaults of the javam package have changed (only 1.5 and 1.6 will be installed). In order to install this package with the changed defaults you should execute for this package:

```
opsi-package-manager -i javavm_1.6.0.12-2.opsi --properties package
```

13.2.10 Activating the new support for the USB and HD-Audio driver

In order to activate the support for USB and HD-Audio drivers you should execute the `create_driver_links.py` script in every OS installation product directory (e.g `/opt/pcbin/install/winxppro`)

13.3 Update 3.2 to 3.3

13.3.1 Documentation

Please read the opsi 3.3 changes documentation in the opsi-manual.

13.3.2 Register of the opsi 3.3 repository

In order to avoid that an update to 3.3 happens accidentally the debian package for opsi 3.3 is in a specific repository. Delete in `/etc/apt/sources.list` the entry:

```
deb http://download.uib.de/debian etch opsi3.2
```

and put in:

For Debian sarge: (no update available. Upgrade to Etch)

For Debian Etch, Ubuntu Dapper/Edgy/Feisty (i386/amd64):


```
deb http://download.uib.de/debian etch opsi3.3
```

Execute `apt-get update`.

13.3.3 Put in the opsi debian packages

Put in the packages with following order:

```
apt-get install opsi-depotserver opsi-configed
```

```
apt-get upgrade
```

If you be asked on upgrading which version of a configuration file you wish to apply you should choose the newest version. If not you should know exactly what you do e.g. you don't choose the newest version because you want an other as the default File31-Backend.

The installation of the opsipxeconfd package may abort with a error which is caused by the old installation, not by the new package. In this case please execute:

```
apt-get install opsi-depotserver
```

If there are still errors, it should help to issue an

```
apt-get install -f
```

13.3.4 Checking the backend configuration

In the file `/etc/opsi/backendManager.d/30_vars.conf` is defined which backend manage of opsi be used (`BACKEND_FILE31`, `BACKEND_FILE`, `BACKEND_LDAP`).

The default backend is `BACKEND_FILE31`.

The backend `BACKEND_FILE` is deprecated - you should change to `BACKEND_FILE31`.

The backend `BACKEND_LDAP` is is not supported by opsi 3.3 yet - you should change to `BACKEND_FILE31` until LDAP-support is available.

In the entry `clientManagingBackend` may be controlled if opsi also assume the local DHCP configuration. This is sensible if the DHCP-server of the opsiserver will be used (default). The accordant entry is:

```
self.clientManagingBackend = [ BACKEND_DHCPD, BACKEND_FILE31 ]
```

If the local DHCP isn't used also the `BACKEND_DHCPD` not required:

```
self.clientManagingBackend = BACKEND_FILE31
```

For the hard- and software inventory you have since opsi 3.3 two possibilities: BACKEND_FILE31 or BACKEND_MYSQL. One of these you have to enter independent which backend is used normally:

```
self.swinventBackend = BACKEND_FILE31
self.hwinventBackend = BACKEND_FILE31
```

For the logging there is since opsi 3.3 a own Backend: BACKEND_FILE31. These you have to enter independent which backend is used normally:

```
self.loggingBackend = BACKEND_FILE31
```

After adapting the backend configuration the 'opsi-confd' has to be restarted:

```
/etc/init.d/opsiconfd restart
```

13.3.5 Import of the new opsi products

Fetch the actual necessary opsi packages in the new package format:

```
cd /home/opsiproducts
wget -r -ll -nc -nd -A '*.opsi' http://download.uib.de/opsi3.3/produkte/essential/upgrade
```

The downloaded package has to be installed on the server to be available for the clients. The interactive installation of an opsi package happen with the aid of the order:

```
opsi-package-manager -i <package file name>
```

The following order install the downloaded packages successive:

```
opsi-package-manager -i *.opsi
```

13.4 Update 3.1 to 3.2

13.4.1 Register of the opsi 3.2 repository

In order to avoid that a update to 3.2 happen accidentally the debian package for opsi 3.2 is in an own repository. Delete in /etc/apt/sources.list the entry:

```
deb http://download.uib.de/debian etch opsi3.1
```

and put in:

For Debian sarge: (no update available. Upgrade to Etch)

For Debian Etch, Ubuntu Dapper/Edgy/Feisty (i386/amd64):

```
deb http://download.uib.de/debian etch opsi3.2
```

Execute `apt-get update`.

13.4.2 Put in the opsi debian packages

Put in the packages with following order:

```
apt-get install opsi-depotserver; apt-get upgrade
```

If you be asked while the upgrade which version of a configuration file you will apply you should choose the newest version. If not you should know exactly what you do e.g. you don't choose the newest version because you want an other as the default File31-Backend.

13.4.3 Import of the new opsi products

Fetch the actual necessary opsi packages in the new package format:

```
cd /home/opsiproducts
wget -r -l1 -nd -A '*.opsi' http://download.uib.de/opsi3.2/produkte/essential/upgrade
```

The downloaded package has to be installed on the server to be available for the clients. The interactive installation of an opsi package happen with the aid of the order:

```
opsiinst <paketname>.opsi
```

The following order install the downloaded packages successive:

```
for paket in *.opsi; do opsiinst -f -q -k $paket; done
```

13.4.4 Checking the backend configuration

In the file `/etc/opsi/backendManager.d/30_vars.conf` is defined which backend manage of opsi be used (`BACKEND_FILE31`, `BACKEND_FILE`, `BACKEND_LDAP`). The default backend is `BACKEND_FILE31`. In the entry `clientManagingBackend` may be controlled if opsi also assume the local DHCP configuration. This is sensible if the DHCP-server of the opiserver will be used (default). The accordant entry is:

```
self.clientManagingBackend = [ BACKEND_DHCPD, BACKEND_FILE31 ]
```

If the local DHCP isn't used also the `BACKEND_DHCPD` not required:

```
self.clientManagingBackend = BACKEND_FILE31
```

For the hard- and software inventory you have to enter the FILE31-backend independent which backend is used normally:

```
self.swinventBackend = BACKEND_FILE31  
self.hwinventBackend = BACKEND_FILE31
```

After adapting the backend configuration the 'opsi-confd' has to be restarted.

13.5 Update 3.0 to 3.1

13.5.1 Register of the opsi3.1 repository

In order to avoid that a update to 3.1 happen accidentally the debian package for opsi 3.1 is in an own repository. Delete in /etc/apt/sources.list the entry:

```
deb http://download.uib.de/debian sarge opsi3.0
```

and put in:

For debian sarge (only i386):

```
deb http://download.uib.de/debian sarge opsi3.1
```

For debian Etch, Ubuntu Dapper/Edgy (i386/amd64):

```
deb http://download.uib.de/debian etch opsi3.1
```

Execute `apt-get update`.

13.5.2 Put in the opsi debian packages

Put in the packages with following order:

```
apt-get install opsi-depotserver; apt-get upgrade
```

If you be asked while the upgrade which version of a configuration file you will apply you should choose the newest version; if not you should know exactly what you do.

13.5.3 Adapt the configuration

Opsi 3.1 used per default the new backend "File31". So you either adapt your configuration that your previous backend will used or the data base from th eold to the new backend convert. The classification of the opsi-backends to the different

„functions“ will be defined in the file `/etc/opsi/backendManager.d/30_vars.conf`. If you want to use the file-backend further the corresponding section has to look like these:

```
self.defaultBackend      = BACKEND_FILE
self.clientManagingBackend = BACKEND_FILE
self.pxebootconfBackend  = BACKEND_OPSIPXECONFD
self.passwordBackend     = BACKEND_FILE
self.pckeyBackend        = BACKEND_FILE
self.hwinventBackend     = BACKEND_FILE
```

In these case it's important that the file-backend further on be loaded. In order to achieve this the line in the file `/etc/opsi/backendManager.d/10_file.conf`:

```
'load': False
```

has to adapted in:

```
'load': True
```

After changing the configuration the services `opsiconfd` and `opsipxeconfd` has to be started new. Execute the following order:

```
/etc/init.d/opsiconfd restart; /etc/init.d/opsipxeconfd restart
```

Should you decide to use the File31-backend the files has to be converted. **Before you convert your system make a backup of your system!** For the conversion of files the program `opsi-convert` will used. The order for a conversion from File- to File31-backend is:

```
opsi-convert File File31
```

After a conversion between the two file based backends the file `/etc/opsi/pckey` should be corrected manually because both backends are using this file but the File31-backend requires entries with fully qualified domain names, e.g.:

```
clientname.domain.tld:1bad67e3c6955ccac891f58ca31ed37e
```

In contrast, the classic File-backend has lines with simple host names, e.g.:

```
clientname:1bad67e3c6955ccac891f58ca31ed37e
```

13.6 Update 2.5 to 3.0

13.6.1 Register of the opsi 3-repository

In order to avoid that an update to 3.0 happens accidentally the debian package for opsi 3.0 is in a special repository. Delete in `/etc/apt/sources` list the entry

```
deb http://download.uib.de/debian sarge main
```

and put in:

```
deb http://download.uib.de/debian sarge opsi3.0
```

Execute `apt-get update`.

13.6.2 Put in the opsi Debian package

Put in the package with the order

```
apt-get install opsi-depotserver opsi-configed opsi-linux-  
bootimage
```

These order should create the following output

```
Reading Package Lists... Done  
Building Dependency Tree... Done  
The following extra packages will be installed:  
  opsi-reinstmgr opsi-utils opsiconfd python python-crypto python-json  
  python-ldap python-newt python-opsi python-pam python-pyopenssl  
  python-twisted python2.3 python2.3-crypto python2.3-ldap python2.3-pam  
  python2.3-pyopenssl python2.3-twisted python2.3-twisted-bin sun-j2re1.6  
Suggested packages:  
  python-doc python-tk python-profiler slapd python-gtk2 python-glade-1.2  
  python-glade2 python-qt3 libwxgtk2.4-python python2.3-doc python2.3-profiler  
  python-ldap-doc pyopenssl-doc  
Recommended packages:  
  python-serial python2.3-iconvcodec python2.3-cjkcodecs  
  python2.3-japanese-codecs  
The following NEW packages will be installed:  
  opsi-configed opsi-reinstmgr opsi-utils opsiconfd python python-crypto  
  python-json python-ldap python-newt python-opsi python-pam python-pyopenssl  
  python-twisted python2.3 python2.3-crypto python2.3-ldap python2.3-pam  
  python2.3-pyopenssl python2.3-twisted python2.3-twisted-bin sun-j2re1.6  
The following packages will be upgraded:  
  opsi-depotserver opsi-linux-bootimage  
2 upgraded, 21 newly installed, 0 to remove and 0 not upgraded.  
Need to get 88.0MB of archives.  
After unpacking 120MB of additional disk space will be used.  
Do you want to continue? [Y/n] Y
```

(.....)

The package `opsiconfd` need some entries to create a SSL-certificate:

```
Setting up opsiconfd (0.9-1) ...  
Generating a 1024 bit RSA private key  
.....+++++  
.....+++++  
writing new private key to '/etc/opsi/opsiconfd.pem'  
-----  
You are about to be asked to enter information that will be incorporated  
into your certificate request.  
What you are about to enter is what is called a Distinguished Name or a DN.  
There are quite a few fields but you can leave some blank
```

```
For some fields there will be a default value,  
If you enter '.', the field will be left blank.
```

```
-----  
Country Name (2 letter code) [AU]:de  
State or Province Name (full name) [Some-State]:Rheinland-Pfalz  
Locality Name (eg, city) []:Mainz  
Organization Name (eg, company) [Internet Widgits Pty Ltd]:uib  
Organizational Unit Name (eg, section) []:  
Common Name (eg, YOUR name) []: opsidepot.uib.local  
Email Address []:info@uib.de
```

```
The user `pcpatch' is already a member of `shadow'.  
Starting opsi config service... (done).
```

(....)

After you finished these chapter go on with 'Inspect the configurations' to 'Put in the minimal opsi-products'.

13.7 Update 2.4 to 2.5

The Update is easy

```
# Informationen über neue Pakete holen  
apt-get update  
# altes depotserver paket entfernen  
apt-get remove opsi-depotserver  
# neue pakete installieren  
apt-get install opsi-depotserver  
apt-get install opsi-webconfigedit  
apt-get install opsi-inied  
# Notwendige opsi-Pakete holen  
wget -r -l 1 -nd -nH --cut-dirs=5 -np -N -R "*.html*" \  
www.uib.de/www/download/download/opsi-pakete/essential  
# notwendige opsi-Pakete installieren  
opsiinst win2k.cpio.gz  
opsiinst winxppro.cpio.gz  
opsiinst opsi-winst.cpio.gz  
opsiinst preloginloader.cpio.gz  
opsiinst softinventory.cpio.gz  
opsiinst opsi-adminutils.cpio.gz  
opsiinst javavm.cpio.gz
```

13.8 Update 2.x to 2.4

The update is time-consuming because the versions before 2.4 working not with debian-packages (or only in parts) and some things have to be installed new.

Specially it's a system software update from 'Debian Woody (3.0)' to 'Debian Sarge (3.1)' and from 'Kernel 2.4' to 'Kernel 2.6'. If you don't know an update with 'apt-get dist-upgrade' and haven't possibilities for testing, it will be better to reinstall the server or to

ask some experts (for example uib).

After warning you now the important facts:

Adapt the file '/etc/apt/sources.list' to install the debian-package out of 'stable' and get extra sources.

Here an example

```
#Standard debian Quellen:
deb http://sunsite.informatik.rwth-aachen.de/ftp/pub/Linux/debian/ stable main
non-free contrib
deb-src http://sunsite.informatik.rwth-aachen.de/ftp/pub/Linux/debian/ stable
main non-free contrib
deb http://non-us.debian.org/debian-non-US stable/non-US main contrib non-free
deb http://security.debian.org/ stable/updates main
#Hier gibts den FreeNX-Server:
deb http://www.linux.lk/~anuradha/nx/ ./
#Alternative Samba Quelle:
deb http://ftp.sernet.de/pub/samba/ debian/
#opsi-Pakete:
deb http://www.uib.de/www/download/download/debian sarge main
```

Update with 'apt-get' the databank package. If this isn't possible, you may have to put a proxy in the file '/etc/apt/apt.conf' or delete one.

Before you can start 'dist-upgrade', you have to correct some dependencies:

```
apt-get install libcrypt-blowfish-pp-perl
apt-get install apache-common
```

Update now the system software:

```
apt-get dist-upgrade
```

Edit the '/etc/login.defs' and put '/opt/bin' in the path.

To proceed on:

```
apt-get install kernel-image-2.6.8-2-686
apt-get install kernel-source-2.6.8
apt-get remove opsi-depotserver
#optional (bei Neuinstallation vorhanden)
apt-get install xfce4
apt-get install wget
apt-get install traceroute
apt-get install nxserver
#-> configuration: custom keys
apt-get install mozilla-firefox
```

Now you have done the most work and could go to chapter 'Installation of a debian (Sarge) system with apt-get'.